



Right to Know Hazardous Substance Fact Sheet

Common Name: **ACETAMIDE**

Synonyms: Acetic Acid Amide; Acetimidic Acid

Chemical Name: Acetamide

Date: January 2008

Revision: January 2017

CAS Number: 60-35-5

RTK Substance Number: 2890

DOT Number: UN 3077

Description and Use

Acetamide is a colorless, crystalline (sand-like) material. It is used in lacquers, explosives, and soldering flux, and as a stabilizer, plasticizer and solvent.

- ▶ **ODOR THRESHOLD=140 to 160 mg/m³**
- ▶ Odor thresholds vary greatly. Do not rely on odor alone to determine potentially hazardous exposures.

Reasons for Citation

- ▶ **Acetamide** is on the Right to Know Hazardous Substance List because it is cited by IARC and EPA.
- ▶ This chemical is on the Special Health Hazard Substance List.

SEE GLOSSARY ON PAGE 5.

FIRST AID

Eye Contact

- ▶ Immediately flush with large amounts of water for at least 15 minutes, lifting upper and lower lids. Remove contact lenses, if worn, while rinsing.

Skin Contact

- ▶ Remove contaminated clothing and wash contaminated skin with water.

Inhalation

- ▶ Remove the person from exposure.
- ▶ Transfer promptly to a medical facility.

EMERGENCY NUMBERS

Poison Control: 1-800-222-1222

CHEMTREC: 1-800-424-9300

NJDEP Hotline: 1-877-927-6337

National Response Center: 1-800-424-8802

EMERGENCY RESPONDERS >>>> SEE BACK PAGE

Hazard Summary

Hazard Rating	NJDHSS	NFPA
HEALTH	2	-
FLAMMABILITY	1	-
REACTIVITY	0	-
CARCINOGEN POISONOUS GASES ARE PRODUCED IN FIRE		

Hazard Rating Key: 0=minimal; 1=slight; 2=moderate; 3=serious; 4=severe

- ▶ **Acetamide** can affect you when inhaled and by passing through the skin.
- ▶ **Acetamide** should be handled as a CARCINOGEN--WITH EXTREME CAUTION.
- ▶ Inhaling **Acetamide** can irritate the nose and throat.
- ▶ **Acetamide** may damage the liver.

Workplace Exposure Limits

No occupational exposure limits have been established for **Acetamide**. However, it may pose a health risk. Always follow safe work practices.

- ▶ **Acetamide** may be a CARCINOGEN in humans. There may be no safe level of exposure to a carcinogen, so all contact should be reduced to the lowest possible level.
- ▶ It should be recognized that **Acetamide** can be absorbed through your skin, thereby increasing your exposure.

Determining Your Exposure

- ▶ Read the product manufacturer's Material Safety Data Sheet (MSDS) and the label to determine product ingredients and important safety and health information about the product mixture.
- ▶ For each individual hazardous ingredient, read the New Jersey Department of Health Hazardous Substance Fact Sheet, available on the RTK Program website (<http://nj.gov/health/workplacehealthandsafety/right-to-know/>) or in your facility's RTK Central File or Hazard Communication Standard file.
- ▶ You have a right to this information under the New Jersey Worker and Community Right to Know Act, the Public Employees Occupational Safety and Health (PEOSH) Act if you are a public worker in New Jersey, and under the federal Occupational Safety and Health Act (OSHA) if you are a private worker.
- ▶ The New Jersey Right to Know Act and the PEOSH Hazard Communication Standard (N.J.A.C. 12:100-7) requires most employers to label chemicals in the workplace and requires public employers to provide their employees with information concerning chemical hazards and controls. The federal OSHA Hazard Communication Standard (29 CFR 1910.1200) requires private employers to provide similar information and training to their employees.

This Fact Sheet is a summary of available information regarding the health hazards that may result from exposure. Duration of exposure, concentration of the substance and other factors will affect your susceptibility to any of the potential effects described below.

Health Hazard Information

Acute Health Effects

The following acute (short-term) health effects may occur immediately or shortly after exposure to **Acetamide**:

- ▶ Inhaling **Acetamide** can irritate the nose and throat.

Chronic Health Effects

The following chronic (long-term) health effects can occur at some time after exposure to **Acetamide** and can last for months or years:

Cancer Hazard

- ▶ **Acetamide** may be a CARCINOGEN in humans since it has been shown to cause liver cancer in animals.
- ▶ Many scientists believe there is no safe level of exposure to a carcinogen.

Reproductive Hazard

- ▶ While **Acetamide** has been tested, it is not classifiable as to its potential to cause reproductive harm.

Other Effects

- ▶ **Acetamide** may damage the liver.

Medical

Medical Testing

If symptoms develop or overexposure is suspected, the following are recommended:

- ▶ Liver function tests

Any evaluation should include a careful history of past and present symptoms with an exam. Medical tests that look for damage already done are not a substitute for controlling exposure.

Request copies of your medical testing. You have a legal right to this information under the OSHA Access to Employee Exposure and Medical Records Standard (29 CFR 1910.1020).

Mixed Exposures

- ▶ More than light alcohol consumption can cause liver damage. Drinking alcohol may increase the liver damage caused by **Acetamide**.

Workplace Controls and Practices

Very toxic chemicals, or those that are reproductive hazards or sensitizers, require expert advice on control measures if a less toxic chemical cannot be substituted. Control measures include: (1) enclosing chemical processes for severely irritating and corrosive chemicals, (2) using local exhaust ventilation for chemicals that may be harmful with a single exposure, and (3) using general ventilation to control exposures to skin and eye irritants. For further information on workplace controls, consult the NIOSH document on Control Banding at www.cdc.gov/niosh/topics/ctrlbanding/.

The following work practices are also recommended:

- ▶ Label process containers.
- ▶ Provide employees with hazard information and training.
- ▶ Monitor airborne chemical concentrations.
- ▶ Use engineering controls if concentrations exceed recommended exposure levels.
- ▶ Provide eye wash fountains and emergency showers.
- ▶ Wash or shower if skin comes in contact with a hazardous material.
- ▶ Always wash at the end of the workshift.
- ▶ Change into clean clothing if clothing becomes contaminated.
- ▶ Do not take contaminated clothing home.
- ▶ Get special training to wash contaminated clothing.
- ▶ Do not eat, smoke, or drink in areas where chemicals are being handled, processed or stored.
- ▶ Wash hands carefully before eating, smoking, drinking, applying cosmetics or using the toilet.

In addition, the following may be useful or required:

- ▶ Use a vacuum or a wet method to reduce dust during clean-up. DO NOT DRY SWEEP.

Personal Protective Equipment

The OSHA Personal Protective Equipment Standard (29 CFR 1910.132) requires employers to determine the appropriate personal protective equipment for each hazard and to train employees on how and when to use protective equipment.

The following recommendations are only guidelines and may not apply to every situation.

Gloves and Clothing

- ▶ Avoid skin contact with **Acetamide**. Wear personal protective equipment made from material which can not be permeated or degraded by this substance. Safety equipment suppliers and manufacturers can provide recommendations on the most protective glove and clothing material for your operation.
- ▶ Safety equipment manufacturers recommend *Rubber* for gloves and DuPont *Tyvek®*, *Tychem® Polycoat*, *QC*, *CPF 1*, *SL* and *CPF 2* as protective materials for clothing.
- ▶ All protective clothing (suits, gloves, footwear, headgear) should be clean, available each day, and put on before work.

Eye Protection

- ▶ Wear eye protection with side shields or goggles.
- ▶ Wear a face shield along with goggles when working with corrosive, highly irritating or toxic substances.
- ▶ Do not wear contact lenses when working with this substance.

Respiratory Protection

Improper use of respirators is dangerous. Respirators should only be used if the employer has implemented a written program that takes into account workplace conditions, requirements for worker training, respirator fit testing, and medical exams, as described in the OSHA Respiratory Protection Standard (29 CFR 1910.134).

- ▶ Use a NIOSH approved respirator with an organic vapor cartridge and particulate prefilters. Increased protection is obtained from full facepiece powered-air purifying respirators.
- ▶ Leave the area immediately if (1) while wearing a filter or cartridge respirator you can smell, taste, or otherwise detect **Acetamide**, (2) while wearing particulate filters abnormal resistance to breathing is experienced, or (3) eye irritation occurs while wearing a full facepiece respirator. Check to make sure the respirator-to-face seal is still good. If it is, replace the filter or cartridge. If the seal is no longer good, you may need a new respirator.
- ▶ Consider all potential sources of exposure in your workplace. You may need a combination of filters, prefilters or cartridges to protect against different forms of a chemical (such as vapor and mist) or against a mixture of chemicals.
- ▶ Where the potential for high exposure exists, use a NIOSH approved supplied-air respirator with a full facepiece operated in a pressure-demand or other positive-pressure mode. For increased protection use in combination with an auxiliary self-contained breathing apparatus operated in a pressure-demand or other positive-pressure mode.

Fire Hazards

If employees are expected to fight fires, they must be trained and equipped as stated in the OSHA Fire Brigades Standard (29 CFR 1910.156).

- ▶ **Acetamide** is a COMBUSTIBLE SOLID.
- ▶ Use dry chemical, CO₂, water spray or foam as extinguishing agent.
- ▶ POISONOUS GASES ARE PRODUCED IN FIRE, including *Nitrogen Oxides*.
- ▶ Use water spray to keep fire-exposed containers cool.

Spills and Emergencies

If employees are required to clean-up spills, they must be properly trained and equipped. The OSHA Hazardous Waste Operations and Emergency Response Standard (29 CFR 1910.120) may apply.

If **Acetamide** is spilled, take the following steps:

- ▶ Evacuate personnel and secure and control entrance to the area.
- ▶ Eliminate all ignition sources.
- ▶ Collect powdered material in the most convenient and safe manner and deposit in sealed containers.
- ▶ Ventilate and wash area after clean-up is complete.
- ▶ It may be necessary to contain and dispose of **Acetamide** as a HAZARDOUS WASTE. Contact your state Department of Environmental Protection (DEP) or your regional office of the federal Environmental Protection Agency (EPA) for specific recommendations.

Handling and Storage

Prior to working with **Acetamide** you should be trained on its proper handling and storage.

- ▶ **Acetamide** reacts with OXIDIZING AGENTS (such as PERCHLORATES, PEROXIDES, PERMANGANATES, CHLORATES, NITRATES, CHLORINE, BROMINE and FLUORINE); STRONG ACIDS (such as HYDROCHLORIC, SULFURIC and NITRIC); STRONG BASES (such as SODIUM HYDROXIDE and POTASSIUM HYDROXIDE); and REDUCING AGENTS.
- ▶ Store in tightly closed containers in a cool, well-ventilated area.

Occupational Health Information Resources

The New Jersey Department of Health, Occupational Health Service, offers multiple services in occupational health. These services include providing informational resources, educational materials, public presentations, and industrial hygiene and medical investigations and evaluations.

For more information, please contact:

New Jersey Department of Health
Right to Know Program
PO Box 368
Trenton, NJ 08625-0368
Phone: 609-984-2202
Fax: 609-984-7407
E-mail: rtk@doh.nj.gov
Web address:
<http://nj.gov/health/workplacehealthandsafety/right-to-know/>

***The Right to Know Hazardous Substance Fact Sheets
are not intended to be copied and sold
for commercial purposes.***

GLOSSARY

ACGIH is the American Conference of Governmental Industrial Hygienists. They publish guidelines called Threshold Limit Values (TLVs) for exposure to workplace chemicals.

Acute Exposure Guideline Levels (AEGs) are established by the EPA. They describe the risk to humans resulting from once-in-a-lifetime, or rare, exposure to airborne chemicals.

Boiling point is the temperature at which a substance can change its physical state from a liquid to a gas.

A **carcinogen** is a substance that causes cancer.

The **CAS number** is unique, identifying number, assigned by the Chemical Abstracts Service, to a specific chemical.

CFR is the Code of Federal Regulations, which are the regulations of the United States government.

A **combustible** substance is a solid, liquid or gas that will burn.

A **corrosive** substance is a gas, liquid or solid that causes destruction of human skin or severe corrosion of containers.

DEP is the New Jersey Department of Environmental Protection.

DOT is the Department of Transportation, the federal agency that regulates the transportation of chemicals.

EPA is the Environmental Protection Agency, the federal agency responsible for regulating environmental hazards.

ERG is the Emergency Response Guidebook. It is a guide for emergency responders for transportation emergencies involving hazardous substances.

Emergency Response Planning Guideline (ERPG) values are intended to provide estimates of concentration ranges where one reasonably might anticipate observing adverse effects.

A **fetus** is an unborn human or animal.

A **flammable** substance is a solid, liquid, vapor or gas that will ignite easily and burn rapidly.

The **flash point** is the temperature at which a liquid or solid gives off vapor that can form a flammable mixture with air.

IARC is the International Agency for Research on Cancer, a scientific group.

Ionization Potential is the amount of energy needed to remove an electron from an atom or molecule. It is measured in electron volts.

IRIS is the Integrated Risk Information System database maintained by federal EPA. The database contains information on human health effects that may result from exposure to various chemicals in the environment.

LEL or Lower Explosive Limit, is the lowest concentration of a combustible substance (gas or vapor) in the air capable of continuing an explosion.

mg/m³ means milligrams of a chemical in a cubic meter of air. It is a measure of concentration (weight/volume).

A **mutagen** is a substance that causes mutations. A **mutation** is a change in the genetic material in a body cell. Mutations can lead to birth defects, miscarriages, or cancer.

NFPA is the National Fire Protection Association. It classifies substances according to their fire and explosion hazard.

NIOSH is the National Institute for Occupational Safety and Health. It tests equipment, evaluates and approves respirators, conducts studies of workplace hazards, and proposes standards to OSHA.

NTP is the National Toxicology Program which tests chemicals and reviews evidence for cancer.

OSHA is the federal Occupational Safety and Health Administration, which adopts and enforces health and safety standards.

PEOSHA is the New Jersey Public Employees Occupational Safety and Health Act, which adopts and enforces health and safety standards in public workplaces.

Permeated is the movement of chemicals through protective materials.

PIH is a DOT designation for chemicals which are Poison Inhalation Hazards.

ppm means parts of a substance per million parts of air. It is a measure of concentration by volume in air.

A **reactive** substance is a solid, liquid or gas that releases energy under certain conditions.

STEL is a Short Term Exposure Limit which is usually a 15-minute exposure that should not be exceeded at any time during a work day.

A **teratogen** is a substance that causes birth defects by damaging the fetus.

UEL or Upper Explosive Limit is the highest concentration in air above which there is too much fuel (gas or vapor) to begin a reaction or explosion.

Vapor Density is the ratio of the weight of a given volume of one gas to the weight of another (usually *Hydrogen*), at the same temperature and pressure.

The **vapor pressure** is a measure of how readily a liquid or a solid mixes with air at its surface. A higher vapor pressure indicates a higher concentration of the substance in air and therefore increases the likelihood of breathing it in.

Common Name: **ACETAMIDE**

Synonyms: Acetic Acid Amide; Acetimidic Acid

CAS No: 60-35-5

Molecular Formula: C₅H₅NO

RTK Substance No: 2890

Description: Colorless, crystalline (sand-like) material

HAZARD DATA

Hazard Rating	Firefighting	Reactivity
2 - Health 1 - Fire 0 - Reactivity DOT#: UN 3077 ERG Guide #: 171 Hazard Class: 9 (Miscellaneous)	Use dry chemical, CO ₂ , water spray or foam as extinguishing agent. POISONOUS GASES ARE PRODUCED IN FIRE, including <i>Nitrogen Oxides</i> . Use water spray to keep fire-exposed containers cool.	Acetamide reacts with OXIDIZING AGENTS (such as PERCHLORATES, PEROXIDES, PERMANGANATES, CHLORATES, NITRATES, CHLORINE, BROMINE and FLUORINE); STRONG ACIDS (such as HYDROCHLORIC, SULFURIC and NITRIC); STRONG BASES (such as SODIUM HYDROXIDE and POTASSIUM HYDROXIDE); and REDUCING AGENTS.

SPILL/LEAKS

Isolation Distance:

Spill: 25 meters (75 feet)

Fire: 800 meters (1/2 mile)

Collect powdered material in the most convenient and safe manner and deposit in sealed containers.

Potential for bioconcentration in aquatic organisms is low.

PHYSICAL PROPERTIES

Odor Threshold:	140 to 160 mg/m ³
Flash Point:	Combustible
Specific Gravity:	1.16 (water = 1)
Vapor Pressure:	10 mm Hg at 221°F (105°C)
Water Solubility:	Soluble
Boiling Point:	430°F (222°C)
Melting Point:	176°F (81°C)
Ionization Potential:	9.65 eV
Molecular Weight:	59.1

EXPOSURE LIMITS

No occupational exposure limits have been established for **Acetamide**.

The Protective Action Criteria values are:

PAC-1 = 21 mg/m³; PAC-2 = 230 mg/m³;

PAC-3 = 1,400 mg/m³

PROTECTIVE EQUIPMENT

Gloves:	Rubber
Coveralls:	DuPont Tyvek®, Tychem® Polycoat, QC, CPF 1, SL, CPF 2 or equivalent
Boots:	No information
Respirator:	Supplied air

HEALTH EFFECTS

Eyes:	No information
Skin:	No information
Inhalation:	Nose and throat irritation
Chronic:	Carcinogen - (Liver) in animals

FIRST AID AND DECONTAMINATION

Remove the person from exposure.

Flush eyes with large amounts of water for at least 15 minutes. Remove contact lenses if worn.

Remove contaminated clothing and wash contaminated skin with water.

Transfer to a medical facility.