

Right to Know Hazardous Substance Fact Sheet

Common Name: ACETONE

Synonyms: Dimethyl Ketone

Chemical Name: 2-Propanone

Date: February 2011 Revision: June 2015

Description and Use

Acetone is a clear, colorless liquid with a sweet odor. It is used as a solvent for fats, oils, waxes, resins, plastics, and varnishes, for making other chemicals, and in nail polish remover.

▶ ODOR THRESHOLD = 13 to 62 ppm

Odor thresholds vary greatly. Do not rely on odor alone to determine potentially hazardous exposures.

Reasons for Citation

- Acetone is on the Right to Know Hazardous Substance List because it is cited by OSHA, ACGIH, DOT, NIOSH, NFPA and EPA.
- ► This chemical is on the Special Health Hazard Substance List.

SEE GLOSSARY ON PAGE 5.

FIRST AID

Eye Contact

Immediately flush with large amounts of water for at least 15 minutes, lifting upper and lower lids. Remove contact lenses, if worn, while rinsing.

Skin Contact

Quickly remove contaminated clothing. Immediately wash contaminated skin with large amounts of soap and water.

Inhalation

- ▶ Remove the person from exposure.
- Begin rescue breathing (using universal precautions) if breathing has stopped and CPR if heart action has stopped.
- Transfer promptly to a medical facility.

EMERGENCY NUMBERS

Poison Control: 1-800-222-1222 CHEMTREC: 1-800-424-9300 NJDEP Hotline: 1-877-927-6337

National Response Center: 1-800-424-8802

CAS Number:	67-64-1
RTK Substance Number:	0006
DOT Number:	UN 1090

EMERGENCY RESPONDERS >>>> SEE LAST PAGE

Hazard Summary					
Hazard Rating	NJDHSS	NFPA			
HEALTH	-	1			
FLAMMABILITY	-	3			
REACTIVITY	-	0			

FLAMMABLE

POISONOUS GASES ARE PRODUCED IN FIRE CONTAINERS MAY EXPLODE IN FIRE

Hazard Rating Key: 0=minimal; 1=slight; 2=moderate; 3=serious; 4=severe

- ► Acetone can affect you when inhaled and may be absorbed through the skin.
- Acetone can cause skin irritation. Prolonged or repeated exposure can cause drying and cracking of the skin with redness.
- ► Exposure can irritate the eyes, nose and throat.
- Exposure to high concentrations can cause headache, nausea and vomiting, dizziness, lightheadedness and even passing out.
- Acetone may affect the kidneys and liver.
- ► Acetone is a FLAMMABLE LIQUID and a DANGEROUS FIRE HAZARD.

Workplace Exposure Limits

- OSHA: The legal airborne permissible exposure limit (PEL) is **1,000 ppm** averaged over an 8-hour workshift.
- NIOSH: The recommended airborne exposure limit (REL) is **250 ppm** averaged over a 10-hour workshift.
- ACGIH: The threshold limit value (TLV) is **500 ppm** averaged over an 8-hour workshift <u>and</u> **750 ppm** as a STEL (short-term exposure limit).
- ► The above exposure limits are for air levels only. When skin contact also occurs, you may be overexposed, even though air levels are less than the limits listed above.

Determining Your Exposure

- Read the product manufacturer's Material Safety Data Sheet (MSDS) and the label to determine product ingredients and important safety and health information about the product mixture.
- For each individual hazardous ingredient, read the New Jersey Department of Health Hazardous Substance Fact Sheet, available on the RTK website (<u>http://nj.gov/health/workplacehealthandsafety/right-to-know/</u>) or in your facility's RTK Central File or Hazard Communication Standard file.
- ➤ You have a right to this information under the New Jersey Worker and Community Right to Know Act and the Public Employees Occupational Safety and Health (PEOSH) Act if you are a public worker in New Jersey, and under the federal Occupational Safety and Health Act (OSHA) if you are a private worker.
- The New Jersey Right to Know Act requires most employers to label chemicals in the workplace and requires public employers to provide their employees with information concerning chemical hazards and controls. The federal OSHA Hazard Communication Standard (29 CFR 1910.1200) and the PEOSH Hazard Communication Standard (N.J.A.C. 12:100-7) require employers to provide similar information and training to their employees.

This Fact Sheet is a summary of available information regarding the health hazards that may result from exposure. Duration of exposure, concentration of the substance and other factors will affect your susceptibility to any of the potential effects described below.

Health Hazard Information

Acute Health Effects

The following acute (short-term) health effects may occur immediately or shortly after exposure to **Acetone**:

- ► Acetone can cause skin irritation.
- Exposure can irritate the eyes, nose and throat causing coughing and wheezing.
- Exposure to high concentrations can cause headache, nausea and vomiting, dizziness, lightheadedness and even passing out.

Chronic Health Effects

The following chronic (long-term) health effects can occur at some time after exposure to **Acetone** and can last for months or years:

Cancer Hazard

According to the information presently available to the New Jersey Department of Health, Acetone has not been tested for its ability to cause cancer in animals.

Reproductive Hazard

There is limited evidence that Acetone may damage the male reproductive system (including decreasing the sperm count) and affect female fertility in animals.

Other Effects

- Prolonged or repeated exposure can cause drying and cracking of the skin with redness.
- Acetone may affect the liver and kidneys.
- This chemical has not been adequately evaluated to determine whether repeated exposure can cause brain or other nerve damage. However, many solvents and other petroleum-based chemicals have been shown to cause such damage. Effects may include reduced memory and concentration, personality changes (withdrawal, irritability), fatigue, sleep disturbances, reduced coordination, and/or effects on nerves supplying internal organs (autonomic nerves) and/or nerves to the arms and legs (weakness, "pins and needles").

Medical

Medical Testing

For frequent or potentially high exposure (half the TLV or greater), the following are recommended before beginning work and at regular times after that:

Liver and kidney function tests

If symptoms develop or overexposure is suspected, the following are recommended:

- ► Acetone concentration in the blood, urine, and expired air can be used as an index of exposure.
- ► EEG
- Evaluate for brain effects such as changes in memory, concentration, sleeping patterns and mood (especially irritability and social withdrawal), as well as for headaches and fatigue. Consider evaluations of the cerebellar, autonomic and peripheral nervous systems. Positive and borderline individuals should be referred for neuropsychological testing.

Any evaluation should include a careful history of past and present symptoms with an exam. Medical tests that look for damage already done are <u>not</u> a substitute for controlling exposure.

Request copies of your medical testing. You have a legal right to this information under the OSHA Access to Employee Exposure and Medical Records Standard (29 CFR 1910.1020).

Mixed Exposures

► More than light alcohol consumption can cause liver damage. Drinking alcohol may increase the liver damage caused by Acetone.

Workplace Controls and Practices

Very toxic chemicals, or those that are reproductive hazards or sensitizers, require expert advice on control measures if a less toxic chemical cannot be substituted. Control measures include: (1) enclosing chemical processes for severely irritating and corrosive chemicals, (2) using local exhaust ventilation for chemicals that may be harmful with a single exposure, and (3) using general ventilation to control exposures to skin and eye irritants. For further information on workplace controls, consult the NIOSH document on Control Banding at <u>www.cdc.gov/niosh/topics/ctrlbanding/</u>.

The following work practices are also recommended:

- ► Label process containers.
- ▶ Provide employees with hazard information and training.
- Monitor airborne chemical concentrations.
- Use engineering controls if concentrations exceed recommended exposure levels.
- ▶ Provide eye wash fountains and emergency showers.
- Wash or shower if skin comes in contact with a hazardous material.
- ► Always wash at the end of the workshift.
- Change into clean clothing if clothing becomes contaminated.
- ► Do not take contaminated clothing home.
- Get special training to wash contaminated clothing.
- Do not eat, smoke, or drink in areas where chemicals are being handled, processed or stored.
- ► Wash hands carefully before eating, smoking, drinking, applying cosmetics or using the toilet.

In addition, the following may be useful or required:

Before entering a confined space where Acetone may be present, check to make sure that an explosive concentration does not exist.

Personal Protective Equipment

The OSHA Personal Protective Equipment Standard (29 CFR 1910.132) requires employers to determine the appropriate personal protective equipment for each hazard and to train employees on how and when to use protective equipment.

The following recommendations are only guidelines and may not apply to every situation.

Gloves and Clothing

- Avoid skin contact with Acetone. Wear personal protective equipment made from material which can not be permeated or degraded by this substance. Safety equipment suppliers and manufacturers can provide recommendations on the most protective glove and clothing material for your operation.
- The recommended glove materials for Acetone are Butyl, Silver Shield®/4H® and Barrier®.
- The recommended protective clothing materials for Acetone are Tychem® BR, CSM and TK, and Trellchem® HPS and VPS, or the equivalent.
- ► All protective clothing (suits, gloves, footwear, headgear) should be clean, available each day, and put on before work.

Eye Protection

- Wear indirect-vent, impact and splash resistant goggles when working with liquids.
- If additional protection is needed for the entire face, use in combination with a face shield. A face shield should not be used without another type of eye protection.

Respiratory Protection

Improper use of respirators is dangerous. Respirators should only be used if the employer has implemented a written program that takes into account workplace conditions, requirements for worker training, respirator fit testing, and medical exams, as described in the OSHA Respiratory Protection Standard (29 CFR 1910.134).

- ➤ Where the potential exists for exposure over 250 ppm, use a NIOSH approved full facepiece respirator with an organic vapor cartridge. Increased protection is obtained from full facepiece powered-air purifying respirators.
- ► Leave the area immediately if (1) while wearing a filter or cartridge respirator you can smell, taste, or otherwise detect **Acetone**, (2) while wearing particulate filters abnormal resistance to breathing is experienced, or (3) eye irritation occurs while wearing a full facepiece respirator. Check to make sure the respirator-to-face seal is still good. If it is, replace the filter or cartridge. If the seal is no longer good, you may need a new respirator.
- Consider all potential sources of exposure in your workplace. You may need a combination of filters, prefilters or cartridges to protect against different forms of a chemical (such as vapor and mist) or against a mixture of chemicals.
- Where the potential for high exposure exists, use a NIOSH approved supplied-air respirator with a full facepiece operated in a pressure-demand or other positive-pressure mode. For increased protection use in combination with an auxiliary self-contained breathing apparatus or an emergency escape air cylinder.
- ► Exposure to **2,500 ppm** is immediately dangerous to life and health. If the possibility of exposure above **2,500 ppm** exists, use a NIOSH approved self-contained breathing apparatus with a full facepiece operated in a pressuredemand or other positive-pressure mode equipped with an emergency escape air cylinder.

Fire Hazards

If employees are expected to fight fires, they must be trained and equipped as stated in the OSHA Fire Brigades Standard (29 CFR 1910.156).

- ► Acetone is a FLAMMABLE LIQUID.
- ► Use dry chemical, CO₂, water spray or alcohol-resistant foam as extinguishing agents.
- ► Water may not be effective in fighting fires.
- ▶ POISONOUS GASES ARE PRODUCED IN FIRE.
- CONTAINERS MAY EXPLODE IN FIRE.
- ▶ Use water spray to keep fire-exposed containers cool.
- Vapor is heavier than air and may travel a distance to cause a fire or explosion far from the source and flashback.
- ► Acetone may form an ignitable vapor/air mixture in closed tanks or containers.

Spills and Emergencies

If employees are required to clean-up spills, they must be properly trained and equipped. The OSHA Hazardous Waste Operations and Emergency Response Standard (29 CFR 1910.120) may apply.

- If **Acetone** is spilled or leaked, take the following steps:
- Evacuate personnel and secure and control entrance to the area.
- ► Eliminate all ignition sources.
- Absorb liquids in dry sand, earth, or a similar material and place into sealed containers for disposal.
- Ventilate area of spill or leak.
- ► Keep Acetone out of confined spaces, such as sewers, because of the possibility of an explosion.
- ► DO NOT wash into sewer.
- It may be necessary to contain and dispose of Acetone as a HAZARDOUS WASTE. Contact your state Department of Environmental Protection (DEP) or your regional office of the federal Environmental Protection Agency (EPA) for specific recommendations.

Handling and Storage

Prior to working with **Acetone** you should be trained on its proper handling and storage.

- Acetone may explode when mixed with NITROSYL PERCHLORATE; and CHLOROFORM or BROMOFORM in the presence of a BASE.
- Acetone reacts with OXIDIZING AGENTS (such as PERCHLORATES, PEROXIDES, PERMANGANATES, CHLORATES, NITRATES, CHLORINE, BROMINE and FLUORINE); ACETIC ACID; and NITRIC ACID to form explosive peroxides.
- Store in tightly closed containers in a cool, well-ventilated area.
- ► Acetone attacks PLASTICS.
- ► Sources of ignition, such as smoking and open flames, are prohibited where **Acetone** is used, handled, or stored.
- Metal containers involving the transfer of Acetone should be grounded and bonded.
- ► Use explosion-proof electrical equipment and fittings wherever **Acetone** is used, handled, manufactured, or stored.
- Use only non-sparking tools and equipment, especially when opening and closing containers of Acetone.

Occupational Health Information Resources

The New Jersey Department of Health and Occupational Health Service, offers multiple services in occupational health. These services include providing informational resources, educational materials, public presentations, and industrial hygiene and medical investigations and evaluations.

For more information, please contact:

New Jersey Department of Health Right to Know PO Box 368 Trenton, NJ 08625-0368 Phone: 609-984-2202 Fax: 609-984-7407 E-mail: <u>rtk@doh.nj.gov</u> Web address: http://nj.gov/health/workplacehealthandsafety/right-toknow/

The Right to Know Hazardous Substance Fact Sheets are not intended to be copied and sold for commercial purposes.

ACETONE

GLOSSARY

ACGIH is the American Conference of Governmental Industrial Hygienists. They publish guidelines called Threshold Limit Values (TLVs) for exposure to workplace chemicals.

Acute Exposure Guideline Levels (AEGLs) are established by the EPA. They describe the risk to humans resulting from once-in-a lifetime, or rare, exposure to airborne chemicals.

Boiling point is the temperature at which a substance can change its physical state from a liquid to a gas.

A carcinogen is a substance that causes cancer.

The **CAS number** is unique, identifying number, assigned by the Chemical Abstracts Service, to a specific chemical.

CFR is the Code of Federal Regulations, which are the regulations of the United States government.

A combustible substance is a solid, liquid or gas that will burn.

A **corrosive** substance is a gas, liquid or solid that causes destruction of human skin or severe corrosion of containers.

The **critical temperature** is the temperature above which a gas cannot be liquefied, regardless of the pressure applied.

DEP is the New Jersey Department of Environmental Protection.

DOT is the Department of Transportation, the federal agency that regulates the transportation of chemicals.

EPA is the Environmental Protection Agency, the federal agency responsible for regulating environmental hazards.

ERG is the Emergency Response Guidebook. It is a guide for emergency responders for transportation emergencies involving hazardous substances.

Emergency Response Planning Guideline (ERPG) values provide estimates of concentration ranges where one reasonably might anticipate observing adverse effects.

A fetus is an unborn human or animal.

A **flammable** substance is a solid, liquid, vapor or gas that will ignite easily and burn rapidly.

The **flash point** is the temperature at which a liquid or solid gives off vapor that can form a flammable mixture with air.

IARC is the International Agency for Research on Cancer, a scientific group.

Ionization Potential is the amount of energy needed to remove an electron from an atom or molecule. It is measured in electron volts.

IRIS is the Integrated Risk Information System database on human health effects that may result from exposure to various chemicals, maintained by federal EPA.

LEL or **Lower Explosive Limit**, is the lowest concentration of a combustible substance (gas or vapor) in the air capable of continuing an explosion.

mg/m³ means milligrams of a chemical in a cubic meter of air. It is a measure of concentration (weight/volume).

A **mutagen** is a substance that causes mutations. A **mutation** is a change in the genetic material in a body cell. Mutations can lead to birth defects, miscarriages, or cancer.

NFPA is the National Fire Protection Association. It classifies substances according to their fire and explosion hazard.

NIOSH is the National Institute for Occupational Safety and Health. It tests equipment, evaluates and approves respirators, conducts studies of workplace hazards, and proposes standards to OSHA.

NTP is the National Toxicology Program which tests chemicals and reviews evidence for cancer.

OSHA is the federal Occupational Safety and Health Administration, which adopts and enforces health and safety standards.

PEOSHA is the New Jersey Public Employees Occupational Safety and Health Act, which adopts and enforces health and safety standards in public workplaces.

Permeated is the movement of chemicals through protective materials.

ppm means parts of a substance per million parts of air. It is a measure of concentration by volume in air.

Protective Action Criteria (PAC) are values established by the Department of Energy and are based on AEGLs and ERPGs. They are used for emergency planning of chemical release events.

A **reactive** substance is a solid, liquid or gas that releases energy under certain conditions.

STEL is a Short Term Exposure Limit which is usually a 15minute exposure that should not be exceeded at any time during a work day.

A **teratogen** is a substance that causes birth defects by damaging the fetus.

UEL or **Upper Explosive Limit** is the highest concentration in air above which there is too much fuel (gas or vapor) to begin a reaction or explosion.

Vapor Density is the ratio of the weight of a given volume of one gas to the weight of another (usually *Air*), at the same temperature and pressure.

The **vapor pressure** is a force exerted by the vapor in equilibrium with the solid or liquid phase of the same substance. The higher the vapor pressure the higher concentration of the substance in air.



Common Name: ACETONE

Synonyms: Dimethyl Ketone; 2-Propanone CAS No: 67-64-1 Molecular Formula: C_3H_6O RTK Substance No: 0006

Description: Clear, colorless liquid with a sweet odor

	Н	AZARD D	ATA		
Hazard Rating	Firefighting		Reactivity		
1 - Health 3 - Fire 0 - Reactivity DOT#: UN 1090 ERG Guide #: 127 Hazard Class: 3 (Flammable)	Firefighting FLAMMABLE LIQUID. Use dry chemical, CO ₂ , water spray or alcohol- resistant foam as extinguishing agents. Water may not be effective in fighting fires. POISONOUS GASES ARE PRODUCED IN FIRE. CONTAINERS MAY EXPLODE IN FIRE. Use water spray to keep fire-exposed containers cool. Vapor is heavier than air and may travel a distance to cause a fire or explosion far from the source and flashback. Acetone may form an ignitable vapor/air mixture in closed tanks or containers.		Acetone may explode when mixed with NITROSYL PERCHLORATE; and CHLOROFORM or BROMOFORM in the presence of a BASE. Acetone reacts with OXIDIZING AGENTS (such as PERCHLORATES, PEROXIDES, PERMANGANATES, CHLORATES, NITRATES, CHLORINE, BROMINE and FLUORINE); ACETIC ACID; and NITRIC ACID to form explosive peroxides. Acetone attacks PLASTICS.		
SP	ILL/LEAKS		PH	YSICAL PROPERTIES	
and place into seale Use only non-sparkin Metal containers invo should be grounded Keep Acetone out of sewers, because of DO NOT wash into s aquatic life in high co	2 mile) sand, earth, or a similar material d containers for disposal. g tools and equipment. living the transfer of Acetone and bonded. confined spaces, such as the possibility of an explosion. ewer as Acetone is dangerous to	Odor Thresh Flash Point: LEL: UEL: Auto Ignitio Vapor Dens Vapor Press Specific Gra Water Solut Boiling Poir Freezing Po Ionization P Molecular V	n Temp: ity: sure: avity: bility: bility: at: int: otential: /eight:	13 to 62 ppm -4 °F (-20 °C) 2.5% 12.8% 869 °F (465 °C) 2 (air = 1) 180 mm Hg at 68 °F (20 °C) 0.8 (water = 1) Soluble 133 °F (56 °C) -140 °F (95.6 °C) 9.69 eV 58.1 TECTIVE EQUIPMENT	
OSHA: 1,000 ppm, 8		Gloves:		Silver Shield®/4H® and Barrier® (>8-hr breakthrough)	
NIOSH: 250 ppm, 10- ACGIH: 500 ppm, 8-h IDLH: 2,500 ppm The Protective Action C PAC-1 = 200 ppm	hr TWA r TWA; 750 ppm, STEL riteria values are:	Coveralls: Respirator:	Tyche break >250	em® BR, CSM and TK; Trellchem® HPS and VPS (>8-hr through) ppm - full facepiece APR with <i>Organic vapor cartridges</i> 10 ppm - SCBA	
HEAL	TH EFFECTS	FIF	RST AI	D AND DECONTAMINATION	
wheezir Headac	n nd throat irritation with coughing and	Flush eyes of contact lens Quickly rem amounts of Begin artific	nove the person from exposure. sh eyes with large amounts of water for at least 15 minutes. Remove ntact lenses if worn. ickly remove contaminated clothing and wash contaminated skin with large nounts of soap and water. gin artificial respiration if breathing has stopped and CPR if necessary. nsfer promptly to a medical facility.		